CHEMICAL BONDS

- A CHEMICAL BOND is a strong attractive force between the atoms in a compound.

3 TYPES OF CHEMICAL BOND

Type	Held together by...	Example
Ionic bonds	attractive forces between oppositely charged ions	sodium chloride
Covalent bonds	sharing of valence electrons between two atoms (sometimes more - "delocalized bonds")	water
Metallic bonds *	sharing of valence electrons with all atoms in the metal's structure - make the metal conduct electricity	any metal

*For CHM 110, you don't need to know anything more about metallic bonds than what's in this table. If you take physics, you may learn more about the characteristics of the metallic bond.

... so how can you tell what kind of bond you have? You can use the traditional rules of thumb:

- Metal-Nonmetal bonds will be ionic
- Nonmetal-nonmetal bonds are usually covalent

Metalloids act like NONMETALS, here.

... but for better information about bonding, you can use ELECTRONEGATIVITY.

ELECTRONEGATIVITY:
-A measure of how closely to itself an atom will hold shared electrons

p346: chart

... in other words, how ELECTRON-GREEDY an atom is!

Bonds with ...	are ...	Examples
Little or no difference in electronegativity between atoms	NONPOLAR COVALENT	C-C, C-H, etc.
Larger differences in electronegativity between atoms	* POLAR COVALENT	H-F, C-F, C-Cl, etc.
Very large differences in electronegativity between atoms	IONIC	NaCl, KBr, etc.

* A POLAR bond is a bond where electrons are shared unevenly - electrons spend more time around one atom than another, resulting in a bond with slightly charged ends

ELECTRONEGATIVITY TRENDS

- You may look up elecronegativity data in tables, but it helps to know trends!



Notes:

① - FLUORINE is the most elecronegative element, while FRANCIUM is the least!

② - All the METALS have low electronegativity

③ - HYDROGEN is similar in electronegativity to CARBON

... so C-H bonds tend to be NONPOLAR

(p 346)

DESCRIBING CHEMICAL BONDING

"octet rule"

- a "rule of thumb" (NOT a scienfitic law) predicting how atoms will exchange or share electrons to form chemical compounds

- atoms will gain, lose, or share enough electrons so that they end up with full "s" and "p" subshells in their outermost shell.

- Why "octet"? An "s" subshell can hold two electrons, while a "p" subshell can hold six. 2+6 = 8

IONIC COMPOUNDS

- When atoms react to form IONS, they GAIN or LOSE enough electrons to end up with full "s" and "p" subshells.

example:



Aluminum loses its outer three electrons, and each bromine gains one!

$AlBr_3$

Al^{3+} : [Ne]

Br^- : [Ar]3d¹⁰4s²4p⁶

Br^- : [Ar]3d¹⁰4s²4p⁶

Br^- : [Ar]3d¹⁰4s²4p⁶

... but using electron configurations to describe how aluminum bromide forms is a bit cumbersome! Can we simplify the picture a bit?

LEWIS NOTATION / ELECTRON-DOT NOTATION

- Lewis notation represents each VALENCE electron with a DOT drawn around the atomic symbol. Since the valence shell of an atom contains only "s" and "p" electrons, the maximum number of dots drawn will be EIGHT.

- To use electron-dot notation, put a dot for each valence electron around the atomic symbol. Put one dot on each "side" of the symbol (4 sides), then pair the dots for atoms that have more than four valence electrons.



examples:

More examples

Which "side" you draw the dots on isn't important, as long as you have the right number of electrons and the right number of "pairs"

.. . are all equivalent!

To draw a dot structure for an atom, you need to know HOW MANY valence electrons it has! You can determine this simply from the periodic table, WITHOUT writing the whole electron configuration!



... but how do we use this to describe a reaction that produces ions? Let's look at our previous example!



All of the original valence electrons are gone, so this "dot structure" has no dots!

Each bromide ion has eight outer electrons!

Aluminum loses its outer three electrons (in the 3s and 3p subshells) (leaving it with full 2s and 2p subshells.

Aluminum is oxidized!

Each bromine atom requires one more electron to get a total of eight outer electrons (full "s" and "p" subshells)

Bromine is reduced!

Redox reactions are much clearer when seen using dot notation!

... this is a bit easier to follow than looking at all those letters and numbers in the electron configurations for these elements!

MOLECULAR COMPOUNDS

- Form when atoms SHARE electrons instead of transferring them. This results in the formation of MOLECULES ... groups of atoms held together by electron-sharing.

How might atoms SHARE electrons? By coming together close enough so that their atomic ORBITALS overlap each other:

This idea is called VALENCE BOND THEORY!



Each hydrogen atom has a single electron in a 1s orbital.



When hydrogen atoms come close enough to each other for these orbitals to OVERLAP, each hydrogen "sees" BOTH electrons, filling up the "s" orbitals of both atoms. This is a COVALENT BOND.

Co: together
Valent: valence shells

This is the DIATOMIC MOLECULE, H_2

... so how would this look using dot notation?



a single shared pair of electrons.
This is called a SINGLE BOND

In dot structures, SHARED PAIRS of electrons are often written as DASHES to make the structures look neater.

* Why doesn't hydrogen end up with eight electrons? Because hydrogen has only the first shell, which contains only a single "s" subshell (NO "p" subshell). This "s" subshell is full with two electrons, and that's all hydrogen needs to get.